


DEMS Software Installation Guide


1 Install Microsoft C++ Environment Support, vc_redist.x86

Please note that some steps could be skipped or ignore if you have installed it before.



1.1 Find the “DEMScollector.exe” right click it to run the software as Administrator. (If there any warnings from windows, pls choose allow the software to run. Because the software need permission to disable all shortcut key)

1.2 To install K-lite, just keep clicking “Next” for all steps..











1.3 To install “runtime Pack”, just simply click “Yes”. Sometimes it may take several minutes to response until it finish installation.







2. Install Database mysql-5.5.56-win32











MySQL Server Instance Configuration Wizard

MySQL Server Instance Configuration
Configure the MySQL Server 5.5 server instance.

Please set the networking options.

☒ **Enable TCP/IP Networking**
Enable this to allow TCP/IP connections. When disabled, only local connections through named pipes are allowed.
Port Number: 3306 ☒ Add firewall exception for this port

Please set the server SQL mode.

☒ **Enable Strict Mode**
This option forces the server to behave more like a traditional database server. It is recommended to enable this option.

< Back Next > Cancel

Pls select character set as UTF8

MySQL Server Instance Configuration Wizard

MySQL Server Instance Configuration
Configure the MySQL Server 5.5 server instance.

Please select the default character set.

☐ **Standard Character Set**
Hello! Makes Latin1 the default charset. This character set is suited for English and other West European languages.

☐ **Best Support For Multilingualism**
日本語 Make UTF8 the default character set. This is the recommended character set for storing text in many different languages.

☒ **Manual Selected Default Character Set / Collation**
Please specify the character set to use.
Character Set: utf8

< Back Next > Cancel

MySQL Server Instance Configuration Wizard

MySQL Server Instance Configuration
Configure the MySQL Server 5.5 server instance.

Please set the Windows options.

☒ **Install As Windows Service**
 This is the recommended way to run the MySQL server on Windows.
 Service Name:
☒ Launch the MySQL Server automatically

☒ **Include Bin Directory in Windows PATH**
 Check this option to include the directory containing the server / client executables in the Windows PATH variable so they can be called from the command line.

< Back **Next >** Cancel

IMPORTANT: Please enter root password `!sv5-F40D}bTi!#l`, and select Enable root from remote machines

MySQL Server Instance Configuration Wizard



MySQL Server Instance Configuration
Configure the MySQL Server 5.5 server instance.


Please set the security options.

☒ **Modify Security Settings**
 New root password: Enter the root password.
 Confirm: Retype the password.
☒ **Enable root access from remote machines**

☐ **Create An Anonymous Account**
 This option will create an anonymous account on this server. Please note that this can lead to an insecure system.


< Back Next > Cancel






3. Install DEMS software.


3.1 Keep clicking "Next " to finish installation.






4. Run Video Management Software

4.1 Open folder C:\Program Files (x86)\DEMS-Collector to run the software as Administrator.(If there any warnings from windows, pls choose allow the software to run.





SHALLEYES

User ID

Password

Login Change Password

4.2 Login the software with default Administrator account

User ID: 000000

Password: 123456